

**Note:** This CLAMAV\_MAC file refers to the contents of it's corresponding source tarball and the building/installation of ClamAV.

## AUTO-STARTUP AND INSTALLATION INSTRUCTIONS

~~~~~

These instruction have been tested with versions 0.70 - 0.75.1 and may work with ewer versions as they come out.

If you are using a newer version, examine the conf files and make the corresponding changes

The files included in the CLAMAV\_MAC tarball provide a way to start the service without logging in as well as a way to manually start, stop and reload this service.

First lets set up our user:

```
sudo niutil -create . /groups/clamav
sudo niutil -createprop . /groups/clamav gid 30
sudo niutil -create . /users/clamav
sudo niutil -createprop . /users/clamav uid 30
sudo niutil -createprop . /users/clamav gid 30
sudo niutil -createprop . /users/clamav shell /bin/tcsh
sudo niutil -createprop . /users/clamav home /tmp
sudo niutil -createprop . /users/clamav passwd "*"

```

Build clamav with one of the following commands:

```
./configure --prefix=/usr --mandir=/usr/share/man --sysconfdir=/etc; make; make install

```

```
./configure --mandir=/usr/local/share/man --sysconfdir=/etc; make; make install

```

Move the "CLAMAV" folder to "/System/Library/StartupItems/".

```
sudo chown root:admin /System/Library/StartupItems/CLAMAV/*
sudo chmod 0755 /System/Library/StartupItems/CLAMAV/CLAMAV

```

**Note:** You can also place the folder in /Library/StartupItems/

Move clamav.conf and freshclam.conf from this tarball to "/etc".

Open `/etc/hostconfig` with an editor and insert the following line:

```
CLAMAV=-YES-
```

save the file.

With the flag set to `"-YES-"`, clamav will be enabled at startup.

If you wish to disable auto startup at any time, set `"CLAMAV=-NO-"` in `/private/etc/hostconfig` and it will disable this service and prevent manually starting it.

With the service enabled, you can start, stop and reload the service manually at any time from terminal with one of the following commands:

```
sudo SystemStarter start "CLAMAV"  
sudo SystemStarter stop "CLAMAV"  
sudo SystemStarter reload "CLAMAV"
```

A safety has been built in preventing you from starting the service if you have disabled it in `/private/etc/hostconfig`.

Finally we can set up the folders and log files that clamav needs.

```
sudo mkdir /var/clamav  
sudo chown clamav:clamav /var/clamav  
sudo chmod 0644 /var/clamav  
sudo touch /var/log/clamd.log  
sudo touch /var/log/clam-update.log  
sudo chmod 0644 /var/log/clamd.log  
sudo chmod 0644 /var/log/clam-update.log  
sudo chown clamav /var/log/clamd.log  
sudo chown clamav /var/log/clam-update.log
```

# AGREEMENT

## Copyright (c) 2004 Dale Enterprise L.L.C.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the Dale Enterprise L.L.C. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

### General Provisions

This Agreement sets forth Dale Enterprise L.L.C.'s and its Representatives' entire liability and your exclusive remedy with respect to the Software. You acknowledge that this Agreement is a complete statement of the agreement between you and Dale Enterprise L.L.C. with respect to the Software, and that there are no other prior or contemporaneous understandings, promises, representations, or descriptions with respect to the Software.

This Agreement shall govern any services or content related to the Software, unless such services or content are subject to a separate written agreement between you and Dale Enterprise L.L.C. or its Representatives. However, the limitations of liability and disclaimer of warranties in this Agreement shall apply to Dale Enterprise L.L.C. and its Representatives with respect to such content or services except to the extent provided otherwise in a separate written agreement approved by Dale Enterprise L.L.C. between you and Dale Enterprise L.L.C. or the applicable Representative(s).

This Agreement does not limit any rights that Dale Enterprise L.L.C. may have under trade secret, copyright, patent, or other laws. The Representatives of Dale Enterprise L.L.C. are not authorized to make modifications to this Agreement, or to make any additional representations, commitments, or warranties binding on Dale Enterprise L.L.C., other than in writing signed by an officer of Dale Enterprise L.L.C.. Accordingly, such additional statements are not binding on Dale Enterprise L.L.C. and you should not rely upon such statements. If any provision of this Agreement is invalid or unenforceable under applicable law, then it is, to that extent, deemed omitted and the remaining provisions will continue in full force and effect. The validity and performance of this Agreement shall be governed by Florida law (without reference to choice of law principles), except as to copyright and trademark matters, which are covered by federal laws. This Agreement is deemed entered into at St Petersburg, Florida, and shall be construed as to its fair meaning and not strictly for or against either party.

**LIMITATION OF LIABILITY AND DAMAGES**

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO: DAMAGES FOR LOSS OF BUSINESS, LOSS OF PROFITS OR INVESTMENT, OR THE LIKE), WHETHER BASED ON BREACH OF CONTRACT, BREACH OF WARRANTY, TORT (INCLUDING NEGLIGENCE), PRODUCT LIABILITY OR OTHERWISE, EVEN IF Dale Enterprise L.L.C. OR ITS REPRESENTATIVES HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES, AND EVEN IF A REMEDY SET FORTH HEREIN IS FOUND TO HAVE FAILED OF ITS ESSENTIAL PURPOSE. SOME STATES DO NOT ALLOW THE LIMITATION AND/OR EXCLUSION OF LIABILITY FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATION OR EXCLUSION MAY NOT APPLY TO YOU. THE LIMITATIONS OF DAMAGES SET FORTH ABOVE ARE FUNDAMENTAL ELEMENTS OF THE BASIS OF THE BARGAIN BETWEEN Dale Enterprise L.L.C. AND YOU. Dale Enterprise L.L.C. WOULD NOT BE ABLE TO HAVE PROVIDED THIS SOFTWARE OR SERVICES WITHOUT SUCH LIMITATIONS.